

No: 001
Date: August 1, 2018

Product: WebLink 1.3
Type: Product Update

WebLink® 1.3.0 – Release Notes

Summary:

Omron Microscan's WebLink is the first web browser-based barcode reader interface. This intuitive user interface is compatible with any USB or Ethernet MicroHAWK reader. There's no software to download or install – the software is pre-loaded on the reader. Set up, test, and control any MicroHAWK reader in the web browser of your choice.



Announcement	Description	Benefits
--------------	-------------	----------

Introduction of WebLink 1.3 and the MicroHAWK ID-45 Smart Camera



- **Fast Linear Mode**
- **Power Strobe**
- **Continuous Read Capture**
- **Fast Linear Mode** – Improved 1D reading for high-speed, close-range applications.
- **Power Strobe** – Enables further acceleration of fast-moving production lines for high-speed close-range applications. Strobe operation allows internal or external lighting controls for your application to control the light in sync with image acquisition. The light can be switched on fast enough that it achieves full brightness before the exposure begins.
- **Continuous Rapid Capture** – Removes the need for a user to select a fixed number of captures in trigger mode.

WebLink Features

- A single tool to test, configure, and deploy the MicroHAWK in your application.
- No software download or installation necessary – access WebLink from the web browser of your choice.
- Complete help documentation available within WebLink.

www.microscan.com

GLOBAL HEADQUARTERS OFFICES
 Corporate & Americas
 Renton, WA USA
 Tel: +1 425.226.5700
www.microscan.com

©2018 Omron Microscan Systems, Inc.

WebLink 1.3.0 Bug Fixes

- Updated Quick Focus
- Updated Decode Time reporting
- Updated Gain and Exposure functionality
- Updated Total Read Time tooltip
- Updated Output Formatting Editor
- Added Latch Mode 1 (Unlatch on Setup Button)
- Updated Multi-Language Options
- Updated Microsoft Edge browser support
- Updated Internet Explorer browser support